# OpenCV Python

# Linux Installation Manual



Version 1.0 e-con Systems 09/08/2020



#### **Disclaimer**

e-con Systems reserves the right to edit/modify this document without any prior intimation of whatsoever.



### Contents

| INTRODUCTION TO OPENCY           | 3  |
|----------------------------------|----|
|                                  |    |
| Prerequisites                    | 3  |
| DESCRIPTION                      | 3  |
| BUILDING OPENCV                  | 4  |
| STEP 1 - INSTALLING DEPENDENCIES | 4  |
| STEP 2 - CONFIGURING OPENCV      | 5  |
| BUILDING SAMPLE CODE             | 6  |
| USING PREBUILT BINARY            | 7  |
| TROUBLESHOOTING                  | 8  |
| SUPPORT                          | 10 |



### Introduction to OpenCV

Open Source Computer Vision Library (OpenCV) is an open source computer vision and machine learning software library. OpenCV libraries are used to communicate with Cameras. APIs introduced in the OpenCV can be supported with all e-Con systems cameras.

This document helps to install the OpenCV in Linux and build a sample code to access the camera with OpenCV.

### **Prerequisites**

The prerequisites are as follows:

- Download OpenCV from here (https://github.com/opencv/opencv)
- Or download the official OpenCV release using wget :

```
$ cd ~
$ wget -0 opencv.zip \
https://github.com/opencv/opencv/archive/<3.3.1 or 3.4.1
>.zip
```

- Download OpenCV contrib from here (<u>https://github.com/opencv/opencv\_contrib</u>)
- Or download the official OpenCV contrib release using wget :

\$ wget -0 opencv\_contrib.zip \ https://github.com/opencv/
opencv\_contrib/archive/<3.3.1 or 3.4.1 >.zip

Unzip the archieves

```
$ unzip opencv.zip
$ unzip opencv_contrib.zip
```

- GCC 4.4.
- CMake 2.8.7 or higher.
- GTK+2.x or higher, including headers (libgtk2.0-dev).
- Python 3.6.8.
- Library packages: libjpeg-dev, libpng-dev, libtiff-dev, libjasperdev, libavcodec-dev, libavformat-dev, libswscale-dev, libv4l-dev, libxvidcore-dev, libx264-dev, libgtk-3-dev, libatlas-base-dev, gfortran.

© Copyright e-con Systems. 2020. All rights reserved.



### **Description**

The following steps have been tested on Ubuntu 18.04 (Bionic Beaver) and with Python 3.6.9. OpenCV must work on any other relatively modern version of Linux OS.



## **Building OpenCV**

The OpenCV is a sample command line application used to demonstrate some of the features of the e-con Cameras with OpenCV APIs. The steps to build OpenCV are as follows:

Step 1. <u>Installing Dependencies</u> Step 2. <u>Configuring OpenCV</u>

### **Step 1 - Installing Dependencies**

The below table lists the dependencies to be installed for using OpenCV.

**Table 1: Installing Dependencies** 

| Dependencies   | Commands  |  |
|--|---|--|
| Some general development libraries                             | <pre>\$ sudo apt-get install build-<br/>essential make cmake cmake-qt-<br/>gui g++ unzip pkg-config</pre>   |  |
| Video4Linux Camera development libraries                       | \$ sudo apt-get install libv4l-<br>dev  |  |
| OpenGL development libraries for creating graphical windows    | <pre>\$ sudo apt-get install libglew- dev</pre>   |  |
| GTK development<br>libraries for creating<br>graphical windows | <pre>\$ sudo apt-get install libgtk-3- dev</pre>  |  |
| Udev development libraries for accessing device information    | <pre>\$ sudo apt-get install libudev- dev</pre>   |  |
| Libav video input or<br>output development<br>libraries        | \$ sudo apt-get install libavformat-dev libavutil-dev libswscale-dev libavcodec-dev libavcodec-ffmpeg-extra56 libavformat-ffmpeg56 libavutil-ffmpeg54 libswscale-ffmpeg3 libdc1394-* libjpeg-dev libpng-dev libtiff-dev libjasper-dev libxvidcore-dev libx264-dev |  |
| Eigen3 math development libraries                              | <pre>\$ sudo apt-get install libeigen3-dev</pre>  |  |
| Python 3 headers and libraries                                 | <pre>\$ sudo apt-get install python3.6-dev</pre>  |  |
| Pyudev library   | <pre>\$ sudo python3 -m pip install pyudev</pre>  |  |
| Numpy library  | <pre>\$sudo apt-get install python3- numpy</pre>  |  |

5



### **Step 2 - Configuring OpenCV**

The steps to configure OpenCV are as follows:

- 1. Replace the **videoio** folder inside the downloaded /opencv-<3.3.1 or 3.4.1> /modules directory with the folder provided by e-con Systems in this link (https:/github.com/econsystems/opency/tree/master/Source)
- 2. To build and install OpenCV, go to the downloaded opencv-<3.3.1 or 3.4.1> directory.

```
$ mkdir release
$ cd release
$ cmake -D CMAKE_BUILD_TYPE=RELEASE \
    -D CMAKE_INSTALL_PREFIX=/usr/local \
    -D WITH_CUDA=OFF \
    -D INSTALL_PYTHON_EXAMPLES=ON \
    -D OPENCV_EXTRA_MODULES_PATH=~/<opencv_contrib-(3.3.1 or 3.4.1)>/modules \
    -D OPENCV_ENABLE_NONFREE=ON \
    -D BUILD_EXAMPLES=ON \
    -D BUILD_TESTS=OFF \
    -D WITH_GPHOTO2=OFF \
    -D WITH_VTK=OFF \
    -D BUILD_PERF_TESTS=OFF ...
```

3. To build and install the OpenCV libraries in the location /usr/local/lib/, you must run the following commands.

```
$ sudo make -j4 && sudo make install
```



## **Building Sample Code**

This section describes about how to build the sample code.

The steps to run sample application are as follows:

- 1. Download OpenCV Python sample command line application from here (<a href="https://github.com/econsystems/opencv/tree/master/Source">https://github.com/econsystems/opencv/tree/master/Source</a>).
- 4. To run the sample code, run the following command.

```
$ sudo python3 main.py
```

5. Number of devices connected to the PC will be displayed just as below shown.

7



## Using Prebuilt binary

This section describes about how to build the sample code.

The steps to run sample application are as follows:

- 1. Download OpenCV Python Application package from here (<a href="https://github.com/econsystems/opencv/tree/master/Source">https://github.com/econsystems/opencv/tree/master/Source</a>).
- 2. Go to the source folder.
- 6. To run the sample code, run the following command.

```
$ sudo PYTHONPATH="@path/cv2/" LD_LIBRARY_PATH="@path/
lib" python3 main.py
```

```
*eg:setting cv2 path /Binary/<Opencv_(3.3.1 or 3.4.1)/Linux/
<18.04_x64 or 16.04_x64>/cv2/
```

- \*eg:setting lib path Binary/<Opencv\_(3.3.1 or 3.4.1)/Linux/<18.04\_x64 or 16.04\_x64>/lib
- 7. Number of devices connected to the PC will be displayed just as below shown.



### Troubleshooting

In this section, you can view the list of commonly occurring issues and their troubleshooting steps.

## Camera Device connected, but the application does not displayed.

It seems like the camera is not properly detected by Linux, so check with the path **cd** /sys/class/video4linux/ to detect the device.

### CMake Error: The source directory does not appear to contain CMakeLists.txt.

- 1. Run cmake-gui from the terminal.
- 2. Provide the source and release folder path of the OpenCV project.
- 3. Configure and generate the solution.

### Compiling command line application, libudev.so error adding symbols, DSO missing from command line.

Include the ludev dependency in the compilation command.

Eg: CMAKE\_CXX\_FLAGS="-ludev"

## Camera displays in the command line but selecting the index does not end up with the preview.

Make sure the camera connected to the port starts with video0 /sys/class/video4linux.

### PermissionError: [Errno 13] Permission denied: '/dev/hidraw'.

Provide **sudo** permission to the command.

sudo python3 main.py



#### In Ubuntu 14.04 version, the dependency libraries varies.

Based on the Ubuntu versions, the development libraries will differ, for example in ubuntu 16.04, libavcodec version will be 56, but in ubuntu 14.04 libavcodec version will be 54. Thus, install dependencies which supports the ubuntu versions.

#### Error loading libopency world.so

```
sudo LD_LIBRARY_PATH=<path_to_the_libopencv_world.so>
python3 main.py
```

Instead, if you wish to add the path to libopencv\_world.so, permanently to the library path. Go to /etc/ld.so.conf.d/. Create a config file named opencv.conf, mention the path inside the config file and give the command:

\$ sudo ldconfig

#### ModuleNotFoundError: No module named 'cv2'

```
ramprasath@ramprasath:~/PycharmProjects/opencv_python$ python main.py
Traceback (most recent call last):
   File "main.py", line 4, in <module>
        import display
   File "/home/ramprasath/PycharmProjects/opencv_python/display.py", line 3, in <module>
        import cv2
ModuleNotFoundError: No module named 'cv2'
ramprasath@ramprasath:~/PycharmProjects/opencv_python$
```

Step 1: Be sure to check the site-packages (and even dist-packages) directory for the system install of Python located in /usr/local/lib/python3.6/site-packages/. Make sure (1) there is a cv2.so file in the site-packages directory and (2) its properly symlinked to a valid file.

Step 2: If the cv2.so file is not present, check in your build/lib directory of your OpenCV build. There should be a cv2.so file there (if both cmake and make executed without error). If the cv2.so file is present, manually copy it into both the system site-packages (or dist-packages) directory.

## AttributeError: 'cv2.VideoCapture' object has no attribute 'getDevices'

```
ramprasath@ramprasath:~/PycharmProjects/opencv_python$ sudo python main.py

**********************************

OpenCV Python App Version = 1.0.1

Running in Linux Platform

Traceback (most recent call last):
    File "main.py", line 143, in <module>
        main = MainClass()

File "main.py", line 44, in __init__
        self.main_menu_init()

File "main.py", line 57, in main_menu_init
        device_info = Device.list_devices(self.cap)
    File "/home/ramprasath/PycharmProjects/opencv_python/device.py", line 22, in list_devices
        ret, device_count = cap.getDevices()

AttributeError: 'cv2.VideoCapture' object has no attribute 'getDevices'

ramprasath@ramprasath:~/PycharmProjects/opencv_python$

■
```



This error may come if you installed opency previously without the e-consystems videoio module and the current build and install is not successful. Check in your build/lib directory of your OpenCV build. There should be a cv2.so file there (if both cmake and make executed without error). If the cv2.so file is present, manually copy it into both the system site-packages (or dist-packages) directory.

#### **Undefined reference to main:**

If previous build fails or repeated building of OpenCV may leads to this error.Follow below steps

- 1.Open cmake-gui.
- 2. Provide the source and release folder path of OpenCV project.
- 3. Uncheck OpenCL, Gsteamer and OpenCV test flags.
- 4.Delete opency folders present in "/usr/local/include"
- 5.Replace the videoio module downloaded from <a href="https://github.com/econsystems/opency/tree/master/Source">https://github.com/econsystems/opency/tree/master/Source</a>
- 6.Rebuild OpenCV again.

#### If cv2 module was not builded:

The make was successfully completed but cv2.so module was not builded in "<build folder>/lib/python3" folder.

- 1.Run cmake-gui.
- 2. Provide the source and release folder path of the OpenCV project.
- 3. Search for python
- 4.Edit variabels as shown below and build OpenCV again.

```
BUILD_opencv_python3
BUILD_opencv_python_bindings_generator <
INSTALL_PYTHON_EXAMPLES
                                     ✓
OPENCY_FORCE_PYTHON_LIBS
PYTHON2 EXECUTABLE
                                     /usr/bin/python2.7
PYTHON2_INCLUDE_DIR
PYTHON2_INCLUDE_DIR2
PYTHON2 LIBRARY
PYTHON2_LIBRARY_DEBUG
PYTHON2_NUMPY_INCLUDE_DIRS
PYTHON2 PACKAGES PATH
                                     lib/python2.7/dist-packages
PYTHON3 EXECUTABLE
                                     /usr/bin/python3
PYTHON3_INCLUDE_DIR
                                     /usr/include/python3.6m
PYTHON3 INCLUDE DIR2
PYTHON3 LIBRARY
                                     /usr/lib/x86 64-linux-gnu/libpython3.6m.so
PYTHON3 LIBRARY DEBUG
PYTHON3_NUMPY_INCLUDE_DIRS
                                     /home/vishnumurali/.local/lib/python3.6/site-packages/numpy/core/include
PYTHON3 PACKAGES PATH
                                     lib/python3.6/dist-packages
```

© Copyright e-con Systems. 2020. All rights reserved.



#### **Contact Us**

If you need any support on OpenCV sample application, please contact us using the Live Chat option available on our website - <a href="https://www.e-consystems.com/">https://www.e-consystems.com/</a>

#### **Creating a Ticket**

If you need to create a ticket for any type of issue, please visit the ticketing page on our website -

https://www.e-consystems.com/create-ticket.asp

#### **RMA**

To know about our Return Material Authorization (RMA) policy, please visit the RMA Policy page on our website - <a href="https://www.e-consystems.com/RMA-Policy.asp">https://www.e-consystems.com/RMA-Policy.asp</a>

#### **General Product Warranty Terms**

To know about our General Product Warranty Terms, please visit the General Warranty Terms page on our website - <a href="https://www.e-consystems.com/warranty.asp">https://www.e-consystems.com/warranty.asp</a>



### **Revision History**

| Re      | Date           | Description                         | Author          |
|---------|----------------|-------------------------------------|-----------------|
| V       |                |                                     |                 |
| 1.<br>0 | 19-May-2020    | Initial Draft                       | Ramson Jehu K   |
| 1.<br>1 | 29-July-2020   | Added changes                       | M Vishnu Murali |
| 1.<br>2 | 15-August-2020 | Added changes                       | Murali Mohan M  |
| 1.<br>3 | 08-Sep-2020    | Added few points in troubleshooting | M Vishnu Murali |